



## Water Meter MODBUS Communication Protocol

### 1 Data type and frame format

1.1 Information transmission is asynchronous, in bytes, and each byte is transmitted in an 11-bit format:

Byte format (serial data)	11 bit binary
start bit	1 bit, 0
data bits	8 bits, least significant bit sent first
parity bit	No checksum
Stop bit	1 bit, 1
baud rate	2400 bit/S

The baud rate can be 2400, 4800, or 9600; the parity bit can be dd/even/no parity; the default is 9600 N 8 1 if there are no special instructions when selecting the product.

### 1.2 Frame Format

Name	Codes	Data length
Address code	01H	1 byte
Control code	CTR ( Read -03, write single register -06, write multiple registers -10)	1 byte
Address field	A0、A1	2 byte
Number of registers	L	2 byte
Check code	Modbus-CS check	2 byte

### 2 Instruction function definition

Address	Number of registers	Data meaning	Definition
0001	0002	Positive cumulative flow (R/W)	Four-byte FLOAT type, little endian mode, unit m <sup>3</sup>
0003	0002	Negative cumulative flow (R/W)	Four-byte FLOAT type, little endian mode, unit m <sup>3</sup>
0005	0002	Instantaneous traffic (R)	Four-byte FLOAT type, little endian mode, unit m <sup>3</sup>
0007	0001	Pipe segment status (R)	0055: Empty pipe section 00AA: Pipe section full of water
0008	0002	Remaining traffic (R/W)	Four-byte FLOAT type, little endian mode, unit m <sup>3</sup>
000A	0002	Pressure value (*) (R)	Four-byte FLOAT type, little endian mode, unit Mpa
000C	0002	Temperature value (*) (R)	Four-byte FLOAT type, little endian mode, unit °C
000E	0001	Device address (R/W)	
000F	0003	Communication parameters (R/W)	Baud rate, parity bit, stop bit②③
0012	0004	Meter address (R/W)	
0016	0004	Device time (R/W)	
001A	0002	Battery voltage (R)	Four-byte FLOAT type, little endian mode, unit V
001C	0001	Valve status and	R:



		control (R/W)	0001 valve open 0002 Valve closed 0004 Valve abnormal 0008 Battery low voltage W: 0001 open valve 0002 close valve
001D	0001	Impulse coefficient (R/W)	
001E	0001	Pressure sensor status (*) (R)	

Notice:

- ① (\*) means customized equipment.
- ②Customize device communication parameters:  
Check digit: no check (0000), even check (0004), odd check (0008)  
Stop bits: 1 stop bit (0000), 1.5 stop bits (4000), 2 stop bits (8000)
- ③Common device communication parameters:  
Check digit: no check (0000), even check (0001), odd check (0002)  
Stop bits: 1 stop bit (0000), 1.5 stop bits (0001), 2 stop bits (0002)

Communication protocol application examples

2.1 Read instantaneous traffic

command:

01 03 0005 0002 D4 0A

Address Read command Starting address Number of registers Check  
code

Response:

01 03 00 04 1E 85 0B 3F 13 E6

Address Read command Number of data bytes Data content Check  
code

The instantaneous flow rate is 0.545 m<sup>3</sup>/H.



## 2.2 Read multiple register data

command:

01 03 0001 001D D4 03

Address Read command Starting address Number of registers Check  
code

Response data parsing:

01 // Address

03 // Read control code

3A // Number of bytes 58

A4 70 AD 40 // Positive cumulative flow 5.42m<sup>3</sup>

C2 F5 78 40 // Negative cumulative flow 3.89m<sup>3</sup>

08 AC 1C 3E // Instantaneous traffic 0.153m<sup>3</sup> /H

55 00 // Pipe section status 0055: Empty pipe section

00 00 00 40 // Remaining traffic 2m<sup>3</sup>

DF 4F 5D 3F // Pressure value 0.8645 Mpa

66 66 CA 41 // Temperature value 25.3℃

01 00 // Meter address 0001

80 25 // Baud rate 9600

00 00 // Check bit

00 00 // Stop bit

71 00 05 01 21 00 51 00 //Meter number 51002101050071

02 19 11 01 07 23 20 00 //Time 2023-07-01 11: 19: 02

66 66 66 40 // Battery voltage 3.6V

01 00 // Valve status 0001 Valve open

01 00 // Pulse coefficient 0001

6E 16 // Check code

## 2.3 Write device address

Command:

01 06 00 0E 0200 E969

Address Write command Register address Write data Check code



Response:

02 06 00 0E 0200 13 E6

Address Write command Register address Write data Check code

## 2.4 Control valve

Command:

01 06 00 1C 0200 49 6C

Address Write command Register address Close valve Check code

Response:

01 06 00 1C 0200 49 6C

Address Write command Register address Write data Check code

## 2.5 Modify communication parameters

Command:

01 10 00 0F 00 03 06 C0 12 01 00 00 00  
7E 4F

Address Write command Register address Number of registers Number  
of bytes Data Verification

Response:

01 10 00 0F 00 03 B0 0B

Address Write command Register address Number of registers Check  
code

Data analysis:

C0 12 //Baud rate 4800, expressed in hexadecimal, low bit first

01 00 //Even parity check, expressed in hexadecimal, low bit first

00 00//1 stop bit, expressed in hexadecimal, low bit first